

## General System & Performance Settings

- **Disable Write Caching:** Right-click **This PC > Manage > Disk drives > double-click the drive > uncheck Enable write caching on the device.**
- **Adjust for Best Performance:** Right-click **This PC > Properties > Advanced system settings > Settings (under Performance) > select Adjust for best performance.**
- **Rename Computer and Workgroup:** In **System Properties**, go to the **Computer Name** tab > **Change > type "posuser" for the computer name and "POS" for the Workgroup.**

## Power Management (Device Manager)

- **Human Interface Devices (HID):** In **Device Manager**, right-click each HID device > **Properties > Power Management > uncheck Allow the computer to turn off this device to save power.**
- **Network Adapter:** Right-click your adapter > **Properties > Power Management > uncheck Allow the computer to turn off this device to save power.**
- **Universal Serial Bus (USB) Controllers:** Right-click all listed USB devices > **Properties > Power Management > uncheck Allow the computer to turn off this device to save power.**

## Services Configuration

Set the following services to **Automatic** startup:

- **DNS Client**
- **Function Discovery Resource Publication**
- **SSDP Discovery**
- **UPnP Device Host**

## Network & Sharing Settings

- **Disable IPv6:** Go to **Network and Sharing Center > Change adapter settings > right-click Ethernet > Properties > uncheck Internet Protocol Version 6 (TCP/IPv6).**
- **Configure IPv4:** In **Ethernet Properties**, highlight **Internet Protocol Version 4 (TCP/IPv4)** and select **Properties** to configure.

- **Enable Network Discovery:** Select **Change advanced sharing settings** in the Network and Sharing Center and enable network discovery.
- **Configure C:\ Drive Sharing:** Right-click **C:\ drive** > **Properties** > **Sharing** tab > **Advanced Sharing** > **Permissions** > **Add** > **Find Now** > select **posuser** > check **Full Control**.
- **Configure Desktop Shortcut:** Go to C:\Focus and send Focus.exe to the desktop. Go to properties on the desktop shortcut and set the launch path from one of the below depending on the PCs position.

### **Task Scheduler (Start Focus Task)**

- **Create Basic Task:** Open **Task Scheduler Library** > **Create a Basic Task**.
- **Name the Task:** Type "**Start Focus**" and select **Next**.
- **Set Trigger:** Choose **When I log on**.
- **Set Action:** Choose **Start a program**.
- **Enter Program Path (Choose one based on PC type):**
  - **Focus Station:** C:\Focus\Focus.exe /pc:\focus /lm /analysis
  - **Backup Station:** C:\Focus\Focus.exe /bc:\focus /lm /analysis
  - **Other Stations:** C:\Focus\Focus.exe /lm /analysis
  - **NON-TRADITIONAL:**  
C(WHAT EVER DRIVE):\FocusFILENAME\Focus.exe  
/p\\PCNAME\c\FocusFILENAME  
  
/PC:\FocusFilename /lm /analysis

## General System & Performance Settings

- **Disable Write Caching:** Right-click **This PC** > **Manage** > **Disk drives** > double-click the drive > uncheck **Enable write caching on the device**.
- **Adjust for Best Performance:** Right-click **This PC** > **Properties** > **Advanced system settings** > **Settings** (under Performance) > select **Adjust for best performance**.
- **Rename Computer and Workgroup:** In **System Properties**, go to the **Computer Name** tab > **Change** > type "**posuser**" for the computer name and "**POS**" for the Workgroup.

## Power Management (Device Manager)

- **Human Interface Devices (HID):** In **Device Manager**, right-click each HID device > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.
- **Network Adapter:** Right-click your adapter > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.
- **Universal Serial Bus (USB) Controllers:** Right-click all listed USB devices > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.

## Services Configuration

Set the following services to **Automatic** startup:

- **DNS Client**
- **Function Discovery Resource Publication**
- **SSDP Discovery**
- **UPnP Device Host**

## Network & Sharing Settings

- **Disable IPv6:** Go to **Network and Sharing Center** > **Change adapter settings** > right-click **Ethernet** > **Properties** > uncheck **Internet Protocol Version 6 (TCP/IPv6)**.
- **Configure IPv4:** In **Ethernet Properties**, highlight **Internet Protocol Version 4 (TCP/IPv4)** and select **Properties** to configure.

- **Enable Network Discovery:** Select **Change advanced sharing settings** in the Network and Sharing Center and enable network discovery.
- **Configure C:\ Drive Sharing:** Right-click **C:\ drive** > **Properties** > **Sharing** tab > **Advanced Sharing** > **Permissions** > **Add** > **Find Now** > select **posuser** > check **Full Control**.
- **Configure Desktop Shortcut:** Go to C:\Focus and send Focus.exe to the desktop. Go to properties on the desktop shortcut and set the launch path from one of the below depending on the PCs position.

### **Task Scheduler (Start Focus Task)**

- **Create Basic Task:** Open **Task Scheduler Library** > **Create a Basic Task**.
- **Name the Task:** Type "**Start Focus**" and select **Next**.
- **Set Trigger:** Choose **When I log on**.
- **Set Action:** Choose **Start a program**.
- **Enter Program Path (Choose one based on PC type):**
  - **Focus Station:** C:\Focus\Focus.exe /pc:\focus /lm /analysis
  - **Backup Station:** C:\Focus\Focus.exe /bc:\focus /lm /analysis
  - **Other Stations:** C:\Focus\Focus.exe /lm /analysis
  - **NON-TRADITIONAL:**  
C(WHAT EVER DRIVE):\FocusFILENAME\Focus.exe  
/p\\PCNAME\c\FocusFILENAME  
  
/PC:\FocusFilename /lm /analysis

## General System & Performance Settings

- **Disable Write Caching:** Right-click **This PC > Manage > Disk drives > double-click the drive > uncheck Enable write caching on the device.**
- **Adjust for Best Performance:** Right-click **This PC > Properties > Advanced system settings > Settings (under Performance) > select Adjust for best performance.**
- **Rename Computer and Workgroup:** In **System Properties**, go to the **Computer Name** tab > **Change > type "posuser" for the computer name and "POS" for the Workgroup.**

## Power Management (Device Manager)

- **Human Interface Devices (HID):** In **Device Manager**, right-click each HID device > **Properties > Power Management > uncheck Allow the computer to turn off this device to save power.**
- **Network Adapter:** Right-click your adapter > **Properties > Power Management > uncheck Allow the computer to turn off this device to save power.**
- **Universal Serial Bus (USB) Controllers:** Right-click all listed USB devices > **Properties > Power Management > uncheck Allow the computer to turn off this device to save power.**

## Services Configuration

Set the following services to **Automatic** startup:

- **DNS Client**
- **Function Discovery Resource Publication**
- **SSDP Discovery**
- **UPnP Device Host**

## Network & Sharing Settings

- **Disable IPv6:** Go to **Network and Sharing Center > Change adapter settings > right-click Ethernet > Properties > uncheck Internet Protocol Version 6 (TCP/IPv6).**
- **Configure IPv4:** In **Ethernet Properties**, highlight **Internet Protocol Version 4 (TCP/IPv4)** and select **Properties** to configure.

- **Enable Network Discovery:** Select **Change advanced sharing settings** in the Network and Sharing Center and enable network discovery.
- **Configure C:\ Drive Sharing:** Right-click **C:\ drive** > **Properties** > **Sharing** tab > **Advanced Sharing** > **Permissions** > **Add** > **Find Now** > select **posuser** > check **Full Control**.
- **Configure Desktop Shortcut:** Go to C:\Focus and send Focus.exe to the desktop. Go to properties on the desktop shortcut and set the launch path from one of the below depending on the PCs position.

### **Task Scheduler (Start Focus Task)**

- **Create Basic Task:** Open **Task Scheduler Library** > **Create a Basic Task**.
- **Name the Task:** Type "**Start Focus**" and select **Next**.
- **Set Trigger:** Choose **When I log on**.
- **Set Action:** Choose **Start a program**.
- **Enter Program Path (Choose one based on PC type):**
  - **Focus Station:** C:\Focus\Focus.exe /pc:\focus /lm /analysis
  - **Backup Station:** C:\Focus\Focus.exe /bc:\focus /lm /analysis
  - **Other Stations:** C:\Focus\Focus.exe /lm /analysis
  - **NON-TRADITIONAL:**  
C(WHAT EVER DRIVE):\FocusFILENAME\Focus.exe  
/p\\PCNAME\c\FocusFILENAME  
  
/PC:\FocusFilename /lm /analysis

## General System & Performance Settings

- **Disable Write Caching:** Right-click **This PC** > **Manage** > **Disk drives** > double-click the drive > uncheck **Enable write caching on the device**.
- **Adjust for Best Performance:** Right-click **This PC** > **Properties** > **Advanced system settings** > **Settings** (under Performance) > select **Adjust for best performance**.
- **Rename Computer and Workgroup:** In **System Properties**, go to the **Computer Name** tab > **Change** > type "**posuser**" for the computer name and "**POS**" for the Workgroup.

## Power Management (Device Manager)

- **Human Interface Devices (HID):** In **Device Manager**, right-click each HID device > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.
- **Network Adapter:** Right-click your adapter > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.
- **Universal Serial Bus (USB) Controllers:** Right-click all listed USB devices > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.

## Services Configuration

Set the following services to **Automatic** startup:

- **DNS Client**
- **Function Discovery Resource Publication**
- **SSDP Discovery**
- **UPnP Device Host**

## Network & Sharing Settings

- **Disable IPv6:** Go to **Network and Sharing Center** > **Change adapter settings** > right-click **Ethernet** > **Properties** > uncheck **Internet Protocol Version 6 (TCP/IPv6)**.
- **Configure IPv4:** In **Ethernet Properties**, highlight **Internet Protocol Version 4 (TCP/IPv4)** and select **Properties** to configure.

- **Enable Network Discovery:** Select **Change advanced sharing settings** in the Network and Sharing Center and enable network discovery.
- **Configure C:\ Drive Sharing:** Right-click **C:\ drive** > **Properties** > **Sharing** tab > **Advanced Sharing** > **Permissions** > **Add** > **Find Now** > select **posuser** > check **Full Control**.
- **Configure Desktop Shortcut:** Go to C:\Focus and send Focus.exe to the desktop. Go to properties on the desktop shortcut and set the launch path from one of the below depending on the PCs position.

### **Task Scheduler (Start Focus Task)**

- **Create Basic Task:** Open **Task Scheduler Library** > **Create a Basic Task**.
- **Name the Task:** Type "**Start Focus**" and select **Next**.
- **Set Trigger:** Choose **When I log on**.
- **Set Action:** Choose **Start a program**.
- **Enter Program Path (Choose one based on PC type):**
  - **Focus Station:** C:\Focus\Focus.exe /pc:\focus /lm /analysis
  - **Backup Station:** C:\Focus\Focus.exe /bc:\focus /lm /analysis
  - **Other Stations:** C:\Focus\Focus.exe /lm /analysis
  - **NON-TRADITIONAL:**  
C(WHAT EVER DRIVE):\FocusFILENAME\Focus.exe  
/p\\PCNAME\c\FocusFILENAME  
  
/PC:\FocusFilename /lm /analysis

## General System & Performance Settings

- **Disable Write Caching:** Right-click **This PC** > **Manage** > **Disk drives** > double-click the drive > uncheck **Enable write caching on the device**.
- **Adjust for Best Performance:** Right-click **This PC** > **Properties** > **Advanced system settings** > **Settings** (under Performance) > select **Adjust for best performance**.
- **Rename Computer and Workgroup:** In **System Properties**, go to the **Computer Name** tab > **Change** > type "**posuser**" for the computer name and "**POS**" for the Workgroup.

## Power Management (Device Manager)

- **Human Interface Devices (HID):** In **Device Manager**, right-click each HID device > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.
- **Network Adapter:** Right-click your adapter > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.
- **Universal Serial Bus (USB) Controllers:** Right-click all listed USB devices > **Properties** > **Power Management** > uncheck **Allow the computer to turn off this device to save power**.

## Services Configuration

Set the following services to **Automatic** startup:

- **DNS Client**
- **Function Discovery Resource Publication**
- **SSDP Discovery**
- **UPnP Device Host**

## Network & Sharing Settings

- **Disable IPv6:** Go to **Network and Sharing Center** > **Change adapter settings** > right-click **Ethernet** > **Properties** > uncheck **Internet Protocol Version 6 (TCP/IPv6)**.
- **Configure IPv4:** In **Ethernet Properties**, highlight **Internet Protocol Version 4 (TCP/IPv4)** and select **Properties** to configure.

- **Enable Network Discovery:** Select **Change advanced sharing settings** in the Network and Sharing Center and enable network discovery.
- **Configure C:\ Drive Sharing:** Right-click **C:\ drive** > **Properties** > **Sharing** tab > **Advanced Sharing** > **Permissions** > **Add** > **Find Now** > select **posuser** > check **Full Control**.
- **Configure Desktop Shortcut:** Go to C:\Focus and send Focus.exe to the desktop. Go to properties on the desktop shortcut and set the launch path from one of the below depending on the PCs position.

### **Task Scheduler (Start Focus Task)**

- **Create Basic Task:** Open **Task Scheduler Library** > **Create a Basic Task**.
- **Name the Task:** Type "**Start Focus**" and select **Next**.
- **Set Trigger:** Choose **When I log on**.
- **Set Action:** Choose **Start a program**.
- **Enter Program Path (Choose one based on PC type):**
  - **Focus Station:** C:\Focus\Focus.exe /pc:\focus /lm /analysis
  - **Backup Station:** C:\Focus\Focus.exe /bc:\focus /lm /analysis
  - **Other Stations:** C:\Focus\Focus.exe /lm /analysis
  - **NON-TRADITIONAL:**  
C(WHAT EVER DRIVE):\FocusFILENAME\Focus.exe  
/p\\PCNAME\c\FocusFILENAME  
  
/PC:\FocusFilename /lm /analysis